



Intel Unite® Plugin Upload



Legal Disclaimers and Copyrights

All information provided here is subject to change without notice. Contact your Intel representative to obtain the latest Intel product specifications and roadmaps.

Intel technologies' features and benefits depend on system configuration and may require enabled hardware, software or service activation. Performance varies depending on system configuration. No computer system can be absolutely secure. Check with your system manufacturer or retailer or learn more at intel.com.

You may not use or facilitate the use of this document in connection with any infringement or other legal analysis concerning Intel products described herein. You agree to grant Intel a non-exclusive, royalty free license to any patent claim thereafter drafted which includes subject matter disclosed herein.

No license (express or implied, by estoppel or otherwise) to any intellectual property rights is granted by this document.

The products described may contain design defects or errors known as errata which may cause the product to deviate from published specifications. Current characterized errata are available on request.

Intel disclaims all express and implied warranties, including without limitation, the implied warranties of merchantability, fitness for a particular purpose, and non-infringement, as well as any warranty arising from course of performance, course of dealing, or usage in trade.

Intel, the Intel logo, Intel® Core™ vPro™ processor family are trademarks of Intel Corporation in the United States and/or other countries.

*Other names and brands may be claimed as the property of others



Contents

1	Instructions	4
1.1	Terminology.....	4
1.2	Prerequisites.....	4
1.3	Notes.....	4
1.4	Steps.....	4



1 Instructions

1.1 Terminology

Table 1. Terminology

Term	Description
Admin Portal	The cloud server: https://admin.unitecloud.intel.com/intelunite/admin Or on premises server

1.2 Prerequisites

- Access to the plugin cab file
- Setup an Organization on the Admin Portal
- Setup a Hub Configuration on the admin portal
- The Hub Configuration is Assigned to a Hub Device Group
- **Bluescape Client Application is installed on the target hub(s)**; Bluescape Enterprise for Windows download and instructions found at <https://create.bluescape.com/bluescape-enterprise-activation>

1.3 Notes

The Plugin will fail to upload if it has the same GUID and version number. Plugins should increment the manifest version every time it is built to avoid collisions with older builds.


1.4 Steps

1. Open the [Admin Portal](#)
2. Click on your Organization

Organization
Organization ID: CB46B6A3-99FC-97E9-80BE-79981ECCD034

Edit Organization Delete Organization

3. Click the Device Management Tab
-




4. Click the UPLOAD PACKAGE button




The screenshot shows a dark blue navigation menu on the left with two main sections: 'Device Management' and 'Server Management', both with dropdown arrows. Below these are several menu items: 'HUBS AND CLIENTS', 'CONFIGURATIONS', 'FEATURES/APPS', 'RESERVED PINS', 'CUSTOM METADATA', 'PROVISION DEVICE', and 'AUTO PAIRING MANAGEMENT'. The 'Quick Actions' section contains three panels: 'PAIR HUB' with an empty input field and a 'PAIR HUB' button; 'AUTO PAIRING' with an input field containing 'duration (hours)' and a 'GENERATE TOKEN' button; and 'UPLOAD PACKAGE' with a large blue 'UPLOAD PACKAGE' button highlighted by a red rounded rectangle. Below the button, it says 'Acceptable file type: CAB'.


5. Navigate to and select the Plugin cab file




6. Click Open
7. Wait For the Success Message to Display



8. Click the approve button




9. Click the Device Management Tab




10. Click the UPLOAD PACKAGE button

11. Click the Configurations Link



12. Click the Edit button of the Configuration assigned to the desired Device Group



13. Click the + Icon next to the desired plugin listed under the Available Features/Apps



Edit Configuration

Hub Default Configuration

Save Changes Cancel

Intel Unite® Software Version
Intel Unite® Solution Hub - 4.0.2920.140

filter

filter

- Available Features/Apps 4.0.2920.14
- + Bluescape Plugin**
No description
Version: 4.0.0.0
 - + Intel Unite® Plugin for Skype™ for Business**
No description
Version: 2.6.84.0
 - + AirServer® Plugin 2.0.4 for Intel Unite®**
No description
Version: 2.0.4.39253
 - + ExchangeCalendarReader**
No description
Version: 2.6.84.0
 - + Intel Unite® Plugin for Protected Guest Access**
No description
Version: 2.1.600.0
 - + Unite PTZ Camera and Audio Reference Design**
No description
Version: 1.0.0.6
 - + Intel Unite® Plugin for Schedule View**
No description
Version: 1.1.494--1

- Selected Features/Apps
- File Sharing Module**
No description
Version: 4.0.2920.14
 - Remote View Module (Hub)**
No description
Version: 4.0.2920.14
 - Screen Sharing Module (Hub)**
No description
Version: 4.0.2920.14

14. The Plugin will Move from the Available List to the Selected List with the Icon changing from a + to a -


15. Click the Save Change button

Edit Configuration

Hub Default Configuration

Save Changes Cancel

16. Verify successful installation when launching the Unite Hub environment.



Intel Unite Client

The Bluescape Plugin for Intel Unite also manifests within the Intel Unite Client, which provides a mechanism to launch and close the Bluescape Wall software, similar to the functionality on the hub.